






MachLink mail setup for Apple iOS Mail

Mail is included in iOS on iPhone and iPad.

<ol style="list-style-type: none">1. Open Settings2. Scroll down and tap 'Passwords & Accounts'	 <p>Settings</p> <ul style="list-style-type: none">Passwords & AccountsMailContactsCalendar
<ol style="list-style-type: none">3. Add Account4. Other5. Add Mail Account	 <p>Add Account</p> <p>3.</p> <p>< Accounts Add Account</p> <ul style="list-style-type: none">iCloudExchangeGoogleYAHOO!Aol.Outlook.comOther <p>4.</p> <p>< Add Account Other</p> <p>MAIL</p> <p>5. Add Mail Account</p>
<ol style="list-style-type: none">6. Name: your first and last name – this is what others see when you send email.7. Email: full MachLink email address8. Password: MachLink password9. Description: Machlink – can be changed this is just a label in case you have multiple mail accounts on device.	 <p>Cancel New Account Next</p> <p>Name First Last</p> <p>Email example@machlink.com</p> <p>Password ●●●●●●●●</p> <p>Description Machlink</p>




MachLink mail setup for Apple iOS Mail

<p>10. IMAP should be selected. Scroll down to add incoming mail server information.</p>	<p>The screenshot shows the 'New Account' screen in iOS Mail. At the top, there are 'Cancel', 'New Account', and 'Next' buttons. Below them are two buttons: 'IMAP' (highlighted in blue) and 'POP'. Further down, there are input fields for 'Name' (with a placeholder 'First Last'), 'Email' (with 'example@machlink.com'), and 'Description' (with 'Machlink').</p>
<p>11. INCOMING MAIL SERVER</p> <ul style="list-style-type: none"> • Host Name: mra.machlink.com • User Name: first part of your MachLink email address before the '@' • Password: your MachLink password <p>12. OUTGOING MAIL SERVER</p> <ul style="list-style-type: none"> • Host Name: mail.machlink.com • User Name: first part of your MachLink email address before the '@' • Password: your MachLink 	<p>The screenshot shows the 'New Account' screen with the 'INCOMING MAIL SERVER' and 'OUTGOING MAIL SERVER' sections expanded. The 'INCOMING MAIL SERVER' section has fields for 'Host Name' (mra.machlink.com), 'User Name' (example), and 'Password' (masked with dots). The 'OUTGOING MAIL SERVER' section has fields for 'Host Name' (mail.machlink.com), 'User Name' (example), and 'Password' (masked with dots). 'Cancel', 'New Account', and 'Next' buttons are visible at the top.</p>
<p>13. There will be two prompts "Cannot Connect Using SSL" – answer Yes each time.</p>	<p>The screenshot shows the 'Verifying' screen in iOS Mail. At the top, there is a 'Verifying' header with a circular arrow icon. Below it, there are fields for 'Email' (example@machlink.com) and 'Description' (Machlink). The 'INCOMING MAIL SERVER' section has fields for 'Host Name' (mra.machlink.com), 'User Name' (example), and 'Password' (masked with dots). The 'OUTGOING MAIL SERVER' section has fields for 'Host Name' (mail.machlink.com), 'User Name' (example), and 'Password' (masked with dots). A modal dialog box is overlaid on the screen with the title 'Cannot Connect Using SSL' and the text 'Do you want to try setting up the account without SSL?'. The dialog has 'Yes' and 'No' buttons.</p>



MachLink mail setup for Apple iOS Mail

14. Mail should be enabled – tap Save.



15. Open Mail and it will load your Inbox messages.

